

efi Enterprise Publication Print Suite 

Technique DMI v2.12.10.17 Release Notes
March 2017

Copyright © 1999 - 2017 by Electronics for Imaging, Inc. All Rights Reserved.

EFI Enterprise Publication Print Suite | *Technique DMI Release Notes*

April 2017 Version 2.12.10.17

Document Version 1

This publication is protected by copyright, and all rights are reserved. No part of it may be reproduced or transmitted in any form or by any means for any purpose without express prior written consent from Electronics for Imaging, Inc. Information in this document is subject to change without notice and does not represent a commitment on the part of Electronics for Imaging, Inc.

Patents

This product may be covered by one or more of the following U.S. Patents: 4,716,978, 4,828,056, 4,917,488, 4,941,038, 5,109,241, 5,170,182, 5,212,546, 5,260,878, 5,276,490, 5,278,599, 5,335,040, 5,343,311, 5,398,107, 5,424,754, 5,442,429, 5,459,560, 5,467,446, 5,506,946, 5,517,334, 5,537,516, 5,543,940, 5,553,200, 5,563,689, 5,565,960, 5,583,623, 5,596,416, 5,615,314, 5,619,624, 5,625,712, 5,640,228, 5,666,436, 5,745,657, 5,760,913, 5,799,232, 5,818,645, 5,835,788, 5,859,711, 5,867,179, 5,940,186, 5,959,867, 5,970,174, 5,982,937, 5,995,724, 6,002,795, 6,025,922, 6,035,103, 6,041,200, 6,065,041, 6,112,665, 6,116,707, 6,122,407, 6,134,018, 6,141,120, 6,166,821, 6,173,286, 6,185,335, 6,201,614, 6,215,562, 6,219,155, 6,219,659, 6,222,641, 6,224,048, 6,225,974, 6,226,419, 6,238,105, 6,239,895, 6,256,108, 6,269,190, 6,271,937, 6,278,901, 6,279,009, 6,289,122, 6,292,270, 6,299,063, 6,310,697, 6,321,133, 6,327,047, 6,327,050, 6,327,052, 6,330,071, 6,330,363, 6,331,899, 6,340,975, 6,341,017, 6,341,018, 6,341,307, 6,347,256, 6,348,978, 6,356,359, 6,366,918, 6,369,895, 6,381,036, 6,400,443, 6,429,949, 6,449,393, 6,476,927, 6,490,696, 6,501,565, 6,519,053, 6,539,323, 6,543,871, 6,546,364, 6,549,294, 6,549,300, 6,550,991, 6,552,815, 6,559,958, 6,572,293, 6,590,676, 6,606,165, 6,633,396, 6,636,326, 6,643,317, 6,647,149, 6,657,741, 6,662,199, 6,678,068, 6,707,563, 6,741,262, 6,748,471, 6,753,845, 6,757,436, 6,757,440, 6,778,700, 6,781,596, 6,816,276, 6,825,943, 6,832,865, 6,836,342, RE33,973, RE36,947, D341,131, D406,117, D416,550, D417,864, D419,185, D426,206, D439,851, D444,793.

Trademarks

The APPS logo, AutoCal, Auto-Count, Balance, Best, the Best logo, BESTColor, BioVu, BioWare, ColorPASS, Colorproof, ColorWise, Command WorkStation, CopyNet, Cretachrom, Cretaprint, the Cretaprint logo, Cretaprinter, Cretaroller, DockNet, Digital StoreFront, DirectSmile, DocBuilder, DocBuilder Pro, DocStream, DSFdesign Studio, Dynamic Wedge, EDOX, EFI, the EFI logo, Electronics For Imaging, Entrac, EPCount, EPPhoto, EPRegister, EPStatus, Estimate, ExpressPay, Fabrivu, Fast-4, Fiery, the Fiery logo, Fiery Driven, the Fiery Driven logo, Fiery JobFlow, Fiery JobMaster, Fiery Link, Fiery Prints, the Fiery Prints logo, Fiery Spark, FreeForm, Hagen, Inkintensity, Inkware, Jetrion, the Jetrion logo, LapNet, Logic, MiniNet, Monarch, MicroPress, OneFlow, Pace, PhotoXposure, PressVu, Printcafe, PrinterSite, PrintFlow, PrintMe, the PrintMe logo, PrintSmith, PrintSmith Site, Printstream, Print to Win, Prograph, PSI, PSI Flexo, Radius, Rastek, the Rastek logo, Remoteproof, RIPChips, RIP-While-Print, Screenproof, SendMe, Sincolor, Splash, Spot-On, TrackNet, UltraPress, UltraTex, UltraVu, UV Series 50, VisualCal, VUTEk, the VUTEk logo, and WebTools are trademarks of Electronics For Imaging, Inc. and/or its wholly owned subsidiaries in the U.S. and/or certain other countries.

All other terms and product names may be trademarks or registered trademarks of their respective owners, and are hereby acknowledged.



Table of Contents

- How To Use This Guide 4**
 - Contact Information 4
- Version 2.12.10.17 Fixed Defects 5**
 - Data Collection..... 5
 - Data Collection, Data Collection Link, Paper Monitor5
 - Data Collection Link 5
 - Inventory Management, Paper Monitor 5
 - Paper Monitor..... 6

How To Use This Guide

This guide describes the changes made in EFI Technique DMI version 2.12.10.17.

Before you upgrade your EFI Technique DMI system to version 2.12.10.17, read the descriptions of the changes made to all the modules that you plan to use. Also read about the minimum system requirements and review any changes with other system users, as applicable. If you have any questions about how the changes may affect you or about changes that you must make to your system before you upgrade your system, please contact your EFI Technique DMI Support representative.

Contact Information

EFI Support

Web Site:	https://customer.efi.com/support
UK Phone:	+ 44 (0) 1246-298085
US Phone:	+1-855-EFI-4HLP
E-Mail:	Technique.support@efi.com

Regular USA Service Desk hours are 8:30 AM to 5:00 PM Eastern Time, Monday – Friday.

Regular European Service Desk hours are 8:30 AM to 5:00 PM Greenwich Mean Time (British Summer Time during summer), Monday – Friday.

Note For problems involving infrastructure (i.e., computers, networks, operating systems, backup software, printers, third-party software, etc.), contact the appropriate vendor. EFI cannot support these types of issues.

EFI Professional Services

UK Phone:	+ 44 (0) 113 3836000
------------------	----------------------

EFI Professional Services can help you perform EFI software installations, upgrades, and updates. This group can also help you implement, customize, and optimize your EFI software plus offer a range of training options.

Version 2.12.10.17 Fixed Defects

This section summarizes the defects fixed in EFI Technique DMI version 2.12.10.17 by module, including the corresponding issue number and fix version.

Data Collection

Issue: Duplicates would appear on Paper Usage Report by Job in Inventory Management.

Resolution: Only record a single movement between lifting/ending a job when the next one starts.

Defect | 02667225, 02743003 | TECHNIQUE-5191 | 2.12.10.17

Data Collection, Data Collection Link, Paper Monitor

Issue: Data Collection - 'Subscript out of range' error messages in RSErrs .log files

Module: MainMod, Function: CleanUpDumpFiles, Line: 0

Resolution: New CleanUpDumpFiles routine will now exit if no files are found in the relevant folders.

Defect | TECHNIQUE-6311 | 2.12.10.17

Issue: Currently the DC dumps and auto backups are deleted after X amount of days. We need to make a change so that the files are deleted after X amount have been created rather than amount of days passed. X needs to be definable in DbLink. The Detailed XMLs also need to be deleted.

Resolution: The DC Dumps and Detail XMLs are now deleted based on a new parameter in DBLink called 'NumBackups'.

Defect | TECHNIQUE-5089 | 2.12.10.17

Data Collection Link

Issue: When uploading Output Audit records all records were being retrieved.

Resolution: When uploading Output Audit records we now only open 1 record instead of selecting from the entire table.

Defect | TECHNIQUE-5233 | 2.12.10.17

Inventory Management, Paper Monitor

Issue: Manually entering a reel through paper monitoring and then rejecting it is not being displayed in Inventory Management as expected.

Resolution: When creating a new reel in Paper Monitoring that is not in Inventory, it now assigns the LocationID and 'DateRecd' so it can be seen in certain Inventory Management screens. It will try and use the LocationID from DBLink first and if that doesn't exist, will try and find the top location for the site from SourcingLocations.

Defect | TECHNIQUE-4401 | 2.12.10.17

Paper Monitor

Issue: Negative length and impressions values being reported by paper monitor.

Resolution: Resolved a runtime error that prevented splice information from being correctly recorded.

Defect | [TECHNIQUE-5636](#) | 2.12.10.17

Issue: Currently the system allows you to Scan Sheets into Reelstand and Reels into Sheetfed reelstand which is wrong. System should only allow the scanning of Web stock for Reelstand and Sheetfed stock if Sheetfed RS.

Resolution: Paper Monitoring now validates if trying to load sheets onto a reel stand and vice versa. Additionally, when creating stock directly on the stand, it will now default the stock type to the type of the stand.

Defect | [TECHNIQUE-2805](#) | 2.12.10.17
